

Rametron V4.1.1 Installation Guide

Prerequisites/Requirements

CPU: 4vCPU RAM: 8GB

STORAGE: 100GB

Operating System: Ubuntu-20

Firewall Public Ports: 5080, 5001, 6011, 8080, 1935, 5443, 5554,

4001, 5353, 80.

Step 1. Change to root user

sudo su root cd /root

Step 2. Execute this command

cd && runuser -u root -- bash <(curl -s
https://build.pandoproject.org/installRametron.sh)</pre>

or

For ARM Web Version

Step 2. Execute this command

cd && runuser -u root -- bash <(curl -s https://build.pandoproject.org/installRametronArm.sh)

*Note:- Each time when we reboot the server we must run this command.

cd && runuser -u root -- bash <(curl -s
https://build.pandoproject.org/rametron_restart.sh)</pre>